

	***	HDNG	1130 CORE IMAGE LOADER-CARD		CIL 000
	*				CIL00010
	*		CORE IMAGE LOADER		CIL00010
		ABS			CIL00020
02EE		ORG	0		CIL00040
	*				CIL00050
	*				CIL00060
0000		ZERO	EQU 0		CIL00070
0000 0		TEMP	MDX START		CIL00080
0001 0		MOVE	DC /1004		CIL00090
0002 0		MASK	DC /0000		CIL00100
0003 0			DC /0020		CIL00110
0004 0		READ	DC CHECK		CIL00120
0005 0			DC /0000	A REGISTER BELOW	CIL00130
0006 0		START	LD MASK+1	0000 0000 0010 0000	CIL00140
0007 0			SLA 2	0000 0000 1000 0000	CIL00150
0008 0			STO MASK+1	0000 0000 1000 0000 =MASK+1	CIL00160
0009 0			SLA 2	0000 0010 0000 0000 -	CIL00170
000A 0			STO TEMP	0000 0010 0000 0000 =TEMP	CIL00180
000B 0			A SETUP	0110 0010 0001 1111	CIL00190
000C 0			STO SETUP	0110 0010 0001 1111 =SETUP LD	CIL00200
000D 0			A CHECK	0111 0010 1111 1111	CIL00210
000E 0			STO CHECK	0111 0010 1111 1111 =CHECK MD	CIL00220
000F 0			S AB+1	0111 0010 0000 0001	CIL00230
0010 0			STO AB+1	0111 0010 0000 0001 =AB+1 MD	CIL00240
0011 0			A LOOP	1101 0010 0000 0111	CIL00250
0012 0			STO LOOP	1101 0010 0000 0111	CIL00260
0013 0			A AB	1101 0010 0010 1011	CIL00270
0014 0	J		A AB		CIL00280
0015 0			STO AB	1101 0010 0100 1111	CIL00290
0016 0			LD TEMP	0000 0010 0000 0000	CIL00300
0017 0			A MOVE	0001 0010 0000 0100	CIL00310
0018 0			STO READ+1	0001 0010 0000 0100	CIL00320
0019 0			A TEMP	0001 0100 0000 0100	CIL00330
001A 0			A MASK+1	0001 0100 1000 0100	CIL00340
001B 0			S MOVE	0000 0100 1000 0000	CIL00350
001C 0			STO MASK+1	0000 0100 1000 0000 =MASK+1	CIL00360
001D 0			SRA 1	0000 0010 0100 0000	CIL00370
001E 0			A TEMP	0000 0100 0100 0000	CIL00380
001F 0			A MOVE	0001 0100 0100 0100	CIL00390
0020 0			STO MOVE	0001 0100 0100 0100	CIL00400
0021 0			A SENSE	0001 0101 0000 0111	CIL00410
0022 0			A TEMP	0001 0111 0000 0111	CIL00420
0023 0			STO SENSE	0001 0111 0000 0111	CIL00430
0024 0			LD MASK		CIL00440
0025 0			RTE 27		CIL00450
0026 0			SLA 4		CIL00460
0027 0			RTE 5		CIL00470
0028 0			STO MASK		CIL00480
0029 0		SETUP	LDX 31	LOADS INDEX 2 WITH 31	CIL00490
002A 0			LD FIXIT	LOAD INTER.ROUTINES ADDR.	CIL00500
002B 0			LOOP DC /6006	= STO 2 7 PLACE IRA IN WDS	CIL00510
002C 0			CHECK DC /1000	=MDX 2 -1 THEN SKIPS OVER BRN	CIL00520
002D 0			MDX LOOP	BRNCH BACK TO LOOP	CIL00530
002E 0			XIO MASK	ALLOWS INTER.LEVELS 0-15	CIL00540
002F 0			CARD XIO MOVE-1	STARTS CARD MOVING	CIL00550
0030 0			WAIT MDX WAIT	WAIT FOR INTER., ALSO USED AS	CIL00560
0031 0			INTER BSS 1	INTER. PROCESSING ROUTINE	CIL00570

PAGE  
C1005  
C1006  
C1007  
C1008  
C1009  
C1010  
C1011  
C1012  
C1013  
C1014  
C1015  
C1016  
C1017  
C1018  
C1019  
C1020  
C1021  
C1022  
C1023  
C1024  
C1025  
C1026  
C1027  
C1028  
C1029  
C1030  
C1031  
C1032  
C1033  
C1034  
C1035  
C1036  
C1037  
C1038  
C1039  
C1040  
C1041  
C1042  
C1043  
C1044  
C1045  
C1046  
C1047  
C1048  
C1049  
C1050  
C1051  
C1052  
C1053  
C1054  
C1055  
C1056  
C1057  
C1058  
C1059  
C1060

```
0032 0 0819      XIO      SENSE-1 GET DEVICE STATUS WORD
*
*      THESE INSTRUCTIONS WILL BE OVERLAID DURING
*      EXECUTION OF THE CIL. THIS AREA IS CALLED
*      THE INPUT BUFFER.
*
0033 0 4828      BSC      Z+      IF BIT ZERO OF DSW IS ON, SKIP
0034 0 7004      GO      MDX      COLM      BRNCH TO COLM IF HAVE COL REQ
0035 0 1002      SLA      2
0036 0 4828      EXIT     BSC      Z+
0037 0 70FF      ME      MDX      ME      BRANCH TO ME, HAVE ERROR
0038 0 7015      MDX      MDX      CARD2     NO ERROR, GO EXECUTE CARD JUST
0039 0 08CA      COLM     XIO      READ      READ IN A COLUMN
003A 0 C011      LD      EVEN
003B 0 4804      BSC      E      NO
003C 0 7005      MDX      PACK     GO TO PACK
003D 0 1801      SRA      1
003E 0 D00D      STO      EVEN
003F 0 C0EC      LD      CHECK     GET COLUMN WORD JUST READ IN
0040 0 D0E8      STO      SETUP    SAVE IT IN SETUP
0041 0 7007      MDX      RESET     GO TO RESET
0042 0 1C01      PACK     SLA      1
0043 0 D008      STO      EVEN
0044 0 C0E7      LD      CHECK     GET COLUMN WORD
0045 0 1808      SRA      8      SHIFT IT INTO POSITION
0046 0 8CE2      A      SETUP     ADD ODD COLM WORD TO GET CORE
0047 0 0024      AB      DC      /0024     STO 2 79
0048 0 0CFE      DC      /00FE
0049 0 4878      RESET   BOSC     +-Z
004A 0 0031      FIXIT  DC      INTER    INTER IS INTER ROUTINE ADDR.
004B 0 70FF      SELF   MDX      SELF     WAIT FOR INTERRUPT
004C 0 0032      EVEN   DC      /0032
004D 0 00C3      SENSE  DC      /00C3
004E 0 4878      CARD2  BOSC     +-Z
*
*
*      DATA IN CARD 2 STARTS IN 004F
*
004F 0 0005      SW1    DC      5      DECREMENT COUNTER TO
0050 00 74FF004F  MDX     L      SW1,-1    READ IN ALL BOOTSTRAP
0052 0 70DC      MDX     CARD     CARDS
*
*      THE SECTION BELOW MOVES DATA
*      FROM LOCATION /00D6 TO /0008
*
0053 0 622E      CON    LDX      2 29+17
0054 00 C60000D5  LD      L2     ONE+1
0056 0 D203      STO      2     J-17
0057 0 72FF      MDX      2     -1
0058 0 70FB      MDX      CON+1
0059 0 1C00      NOP
005A 0 1000      NOP
005B 0 7017      MDX      CD
005C 0 00B5      CK      DC      CK1
005D 0 0080      FIX    DC      INT
*
*      END OF INPUT BUFFER
*
```



PAGE 4  
 CIL01760  
 CIL01770  
 CIL01780  
 CIL01790  
 CIL01800  
 CIL01810  
 CIL01820  
 CIL01830  
 CIL01840  
 CIL01850  
 CIL01860  
 CIL01870  
 CIL01880  
 CIL01890  
 CIL01900  
 CIL01910  
 CIL01920  
 CIL01930  
 CIL01940  
 CIL01950  
 CIL01960  
 CIL01970  
 CIL01980  
 CIL01990  
 CIL02000  
 CIL02010  
 CIL02020  
 CIL02030  
 CIL02040  
 CIL02050  
 CIL02060  
 CIL02070  
 CIL02080  
 CIL02090  
 CIL02100  
 CIL02110  
 CIL02120  
 CIL02130  
 CIL02140  
 CIL02150  
 CIL02160  
 CIL02170  
 CIL02180  
 CIL02190  
 CIL02200  
 CIL02210  
 CIL02220  
 CIL02230  
 CIL02240  
 CIL02250  
 CIL02260  
 CIL02270  
 CIL02280  
 CIL02290  
 CIL02300  
 CIL02310  
 CIL02320  
 CIL02330  
 CIL02340

\* PACKS 4 COLUMNS INTO 3 WORDS.  
 \* IT FILLS THE BUFFER CALLED INPUT  
 \*

0095 0 08FA	COLM1	XIO	RED	
0096 0 D0D9		STO	CITST	SET COL. INT. TEST IND.
0097 00 C4000032	LOOP1	LD L	INPUT-1	
0099 0 18D0		RTE	16	
009A 0 C01A		LD	CK1	
009B 0 18D0	GOB	RTE	16	
009C 00 D4800098		STO I	LOOP1+1	
009E 0 18D0		RTE	16	

\* DATA IN CARD 4 STARTS IN 009F  
 \*  
 \*

009F 00 D4000033		STO L	INPUT	
00A1 00 74FC009B		MDX L	GOB,-4	
00A3 0 C0F7		LD	GOB	
00A4 0 F009		EOR	SENS1	
00A5 00 4C1800B0		BSC L	NEW,+-	
00A7 00 74010098		MDX L	LOOP1+1,1	
00A9 00 740100A0		MDX L	GOB+5,1	
00AB 00 74040099		MDX L	GOB-2,4	
00AD 0 4878	WAIT1	BOSC	+Z	
00AE 0 18C0	SENS1	DC	/18C0	
00AF 0 70CE		MDX	WAIT3	WAIT FOR NEXT INT
00B0 00 74100098	NEW	MDX L	GOB,16	
00B2 00 74F40099		MDX L	GOB-2,-12	
00B4 0 70F8		MDX	WAIT1	

\* STORES BUFFER TO CORE  
 \*  
 \*

00B5 0 0000	CK1	DC	0	COLUMN BUFFER (FROM CARD)
00B6 00 C4000035	DAT	LD L	INPUT+2	GET TYPE AND COUNT
00B8 0 E00B		AND	N	REMOVE COUNT
00B9 0 D001		STO	LAB+1	STORE COUNT IN NEXT INST.
00BA 00 66000000	LAB	LDX L2	*-*	LOAD IR2 WITH COUNT
00BC 00 C4000033		LD L	INPUT	GET LOADING ADDRESS
00BE 0 9015		S	ONE	
00BF 0 D003		STO	LOOP3+3	SET UP DATA STORE INSTR.
00C0 00 C6000035	LOOP3	LD L2	INPUT+2	GET DATA WORD
00C2 00 D6000000		STO L2	*-*	STORE DATA WORD
00C4 0 72FF	N	MDX	2 -1	DECR IR2 BY 1, IF COUNT=0 SK
00C5 0 70FA		MDX	LOOP3	CONTINUE LOADING FROM INPUT

\* DATA IN CARD 5 STARTS IN 00C7  
 \*  
 \*

00C6 00 C4000035		LD L	INPUT+2	GET TYPE
00C8 00 4C500004		BOSC L	BSIXX,-	END-OF-PROGRAM TEST
00CA 00 67800067	EOP	LDX I3	INPUT+52	YES - SET IR-3 TO TV ADDR.
00CC 0 0805		XIO	SCR2-1	LAST CARD TEST
00CD 0 1C03		SLA	3	
00CE 0 4828		BSC	+Z	
00CF 0 08A0		XIQ	CFEED-1	YES - FEED OUT
00DC 00 4CC00068		BOSC I	INPUT+53	GO TO EXECUTE
00E2 0 18D0	RTEXX	RTE	16	CONSTANT FOR REST. RTE

0003 0 1703  
0004 0 0001  
0005 0 709D  
0006

SCRIP2 DC /1703 IOCC TO SENSE DSW  
ONE DC /0001  
MDX CD  
ORG /4

CIL0235  
CIL0236  
CIL0237  
CIL0238  
CIL0239  
CIL0240  
CIL0241  
CIL0242  
CIL0243  
CIL0244  
CIL0245  
CIL0246

\*  
\* THIS SECTION WAS LOADED INTO CORE INITIALLY  
\* AT LOC. /0006. IT IS MOVED TO PROPER ADDRESS  
\* DURING EXECUTION OF PROGRAM LABELED CON.  
\* THIS CODING PROCESSES CHECK SUMS, HANDLES  
\* PROGRAM STOP, ACCOMODATES ERRORS, AND  
\* SETS UP THE INTERRUPT TV.  
\*

0004 0 4001  
0005 0 706D  
0006 0 0000  
0007 C 7006  
0008 0 0080  
0009 0 0000  
000A 0 0000  
000B 0 3F00  
000C 0 0080  
000D 0 0006  
000E 0 0CFB  
000F C 08FA  
0010 0 4828  
0011 0 3000  
0012 0 C0F7  
0013 00 4CC00006  
0015 0 C01E  
0016 00 4C1800B6  
0018 00 74010026  
001A 0 6236  
001B 0 C00A  
001C 00 86000032  
001E 0 4802  
001F 0 8007  
0020 0 72FF

BSIXX BSI LEV5 SET RETURN ADDRESS  
MDX CD  
LEV5 DC 0 LEVEL 5 ENTRY  
MDX \*+6 CONTINUE LEVEL 5  
DC INT  
DC 0  
IOCCX DC 0 IOCC TO SENSE  
DC /3F00 CONSOLE STATUS  
DC INT  
DC LEV5  
STO IOCCX SAVE ACCUMULATOR  
XIO IOCCX SENSE CONSOLE STATUS  
BSC Z+ TEST FOR PROGRAM STOP  
WAIT YES - STOP  
LD IOCCX RESTORE ACCUMULATOR  
BOSC I LEV5 RESTART NEW CARD  
CKSUM LD INPUT+1 TEST CARD CHECK SUM  
BSC L DAT,+ IF ZERO, LOAD IMMEDIATELY  
MDX L CDCNT,1 INCR CARD COUNT BY ONE  
LDX 2 54  
LD CDCNT ADD CARD COUNT PLUS  
OTTO A L2 INPUT-1 54 WORDS (72 COLUMNS)  
BSC C IF CARRY,  
A ONE4 ADD ONE  
MDX 2 -1

CIL0247  
CIL0248  
CIL0249  
CIL0250  
CIL0251  
CIL0252  
CIL0253  
CIL0254  
CIL0255  
CIL0256  
CIL0257  
CIL0258  
CIL0259  
CIL0260  
CIL0261  
CIL0262  
CIL0263  
CIL0264  
CIL0265  
CIL0266  
CIL0267  
CIL0268  
CIL0269  
CIL0270  
CIL0271  
CIL0272

\*  
\* DATA IN CARD 6 STARTS IN /00EF  
\*

0021 0 70FA  
0022 0 9C04  
0023 00 4C1800B6  
0025 0 3000  
0026 0 0000  
0027 0 0001  
0028 00 4C180015  
002A 0 C045  
002B 00 4C200030  
002D 00 74FF0026  
002F 0 1000  
0030 0 1810  
0031 0 7C60

MDX OTTC  
S ONE4 MAKE TWOS COMPLEMENT  
BSC L DAT,+ TEST FOR ZERO  
CK3 WAIT NO - CHECK SUM ERROR  
CDCNT DC 0  
ONE4 DC 1  
FDCHK BSC L CKSUM,+ BRANCH IF NO READER ERROR  
LD CITST GET COL. INT. INDICATOR  
BSC L \*+3,Z TEST FOR ANY COL. INTS.  
MDX L CDCNT,-1 NO, REDUCE CARD COUNT FOR  
NOP RE-READ OF CARD IN FEED  
SRA 16 YES, CLEAR ACCUM.  
MDX ERSTP

CIL0273  
CIL0274  
CIL0275  
CIL0276  
CIL0277  
CIL0278  
CIL0279  
CIL0280  
CIL0281  
CIL0282  
CIL0283  
CIL0284  
CIL0285  
CIL0286  
CIL0287  
CIL0288

0033  
0032 0 0000  
NO ERRORS

\*  
\* INPUT EQU 51 INPUT BUFFER ADDRESS  
END TEMP

CIL0289  
CIL0290  
CIL0291